<u>การตั้งค่าใช้งาน WIFI-RMUTP-STAFF ที่ใช้ระบบปฏิบัติการ Windows 8/8.1</u>

ขั้นตอนการตั้งค่าใช้งาน SSID – WIFI-RMUTP-STAFF สำหรับบนคอมพิวเตอร์ และโน๊ตบุ๊ค ที่ใช้ระบบปฏิบัติการ WINDOWS 8/8.1 ซึ่งต้องมีการตั้งค่าก่อนถึง จะสามารถเข้าใช้งานได้ไม่เหมือน WINDOWS 7 ที่สามารถเข้าใช้งานได้ทันที

 ไปที่หน้า Control panel ที่มุมขวา view by เลือกเป็น small icon และ คลิกที่ Network and Sharing Center



2. ที่หน้า Network and Sharing Center เลือกที่ Set up a new connection or

network

and Sharing Center Nation and set up co	v C	Search Control Panel	Q,
nation and set up co	onnections		
rrently not connected to	any networks.		
work r VPN connection; or set	up a router or access	point.	
roblems, or get troublesh	nooting information.		
	VPN connection; or set	· VPN connection; or set up a router or access roblems, or get troubleshooting information.	VPN connection; or set up a router or access point. roblems, or get troubleshooting information.

3. เลือกที่ Manually connect to a wireless network และกด Next

	-		x
📀 🔄 Set Up a Connection or Network			
Choose a connection option			
Set up a broadband or dial-up connection to the Internet.			
Set up a new network Set up a new router or access point.			
Manually connect to a wireless network Connect to a hidden network or create a new wireless profile.			
Set up a dial-up or VPN connection to your workplace.			
Ν	ext	Canc	el

4. ทำการตั้งค่าดังรูป และกด next

		- 🗆 🗙
📀 😫 Manually connect	t to a wireless network	
Enter information f	or the wireless network y	ou want to add
Network name:	WIFI-RMUTP-STAFF	🗌 ทำการใส่
Security type:	WPA2-Enterprise	🕑 ข้อมูลตามนี้
Encryption type:	AES	~ ~
Security Key:		Hide characters
✓ Start this connecti	on automatically	
Connect even if th	e network is not broadcasting	
Warning: If you se	lect this option, your computer	s privacy might be at risk.
		Next Cancel

5.เลือก Change connection settings

	_ 🗆	×
) See Manually connect to a wireless network		
Successfully added WIFI-RMUTP-STAFF		
 Change connection settings Open the connection properties so that I can change the settings. 		
	Clo	ose

6. คลิกที่ Security



7. คลิกที่ Setting

WIFI-RMUTP-STAI	F Wireless Network Properties	x
Connection Security		
Security type:	WPA2-Enterprise V	
Encryption type:	AES 🗸	
Choose a network aut	hentication method:	
Microsoft: Protected	EAP (PEAP) V Settings	
✓ Remember my creative Time Tim logged on	lentials for this connection each	
Advanced settings		
	OK Cance	2

8. ให้ติกเครื่องหมายถูกที่ช่อง Verify the server's identity by...... ออก และกด OK

Protected EAP Properties	x
When connecting:	
- Verify the server's identity by validating the certificate	
Connect to these servers (examples:srv1;srv2;.*\.srv3\.com):	
Trusted Root Certification Authorities:	
AddTrust External CA Root	
Class 2 Primary CA	
Class 3 Public Primary Certification Authority	
DigiCert Assured ID Root CA	
DigiCert High Assurance EV Root CA	
< >>	
Notifications before connecting:	
Tell user if the server's identity can't be verified	
Select Authentication Method:	_
Secured password (EAP-MSCHAP v2) V Configure	
Enable Fast Reconnect	
Enforce Network Access Protection Disconnect if server does not present cryptobinding TLV	
Enable Identity Privacy	
OK Cancel	

9. คลิกที่ Advanced settings

WIFI-RMUTP-STA	FF Wireless Netwo	ork Properties	×
Connection Security			
Security type:	WPA2-Enterprise	*	
Encryption type:	AES	~	
Choose a network aut	hentication method:		
Microsoft: Protected	EAP (PEAP) ∨	Settings	
 Remember my creative time I'm logged on 	dentials for this connecti	on each	
Advanced settings			
	(OK Can	cel

10. ให้ติกเครื่องหมายถูกที่ช่อง Specify authentication mode ถัดลงมาให้เลือก คำว่า User authentication และกด save credentials จะปรากฏกรอบให้ใส่ Username และ Password ที่เข้าใช้อินเทอร์เนต จากนั้น กด OK ทุกหน้าต่าง ปิด หน้าต่างที่เปิดไว้ให้หมด

WIFI-RMUTP-STAFF Wireless Network Properties
Connection Security
Advanced settings ×
E 802.1X settings 802.11 settings
Specify authentication mode:
User authentication V Save credentials
Delete credentials for all users
windows Security
Save credentials Saving your credentials allows your computer to connect to the network when you're not logged on (for example, to download updates).
User name
Password
OK Cancel

11. ทำการ คลิกที่มุมขวาล่างของจอที่สัญลักษณ์ตามรูป



 12. จะเจอ ชื่อ SSID WIFI-RMUTP-STAFF ถ้าติกที่ช่อง Connect automatically เมื่อเปิดเครื่องขึ้นมาใหม่จะทำการเชื่อมต่ออัตโนมัติให้ทันที เมื่อติก แล้วให้เลือกที่ Connect

Networks
View Connection Settings
Wi-Fi
WIFI-RMUTP-STAFF
Connect automatically
Connect

13. เมื่อเชื่อมต่อสำเร็จแล้วจะปรากฎข้อความ Connected ดังรูป

